Installation of G8BPQ User Mode Virtual Serial Port Driver on Windows 7 and above

Open Device Manager (right click My Computer, and select "Device Manager" Then Right Click on your computer name, and select "Add legacy hardware"

🚔 Device Manager	
File Action View Help	
Scan for hardware changes Add legacy hardware Disk drives Display adapters DVD/CD-ROM drives Human Interface Devices Human Interface Devices IDE ATA/ATAPI controllers Imaging devices Jungo H	•
 Lenovo RMCT Device Mice and other pointing devices Monitors Multi-port serial adapters Network adapters Broadcom NetLink (TM) Fast Ethernet gogo6 Virtual Multi-Tunnel Adapter TAP-Win32 Adapter V8 (coLinux) TAP-Win32 Adapter V9 (coLinux) #2 TAP-Win32 Adapter V9 #2 Portable Devices Ports (COM & LPT) Processors Sound, video and game controllers System devices ACPI Fixed Feature Button 	Ţ
Add Hardware	



wizaro can heip you install other hardware	•
The wizard can search for other hardware and know exactly which hardware model you war	automatically install it for you. Or, if you it to install, you can select it from a list.
What do you want the wizard to do?	
\bigcirc Search for and install the hardware automatic sector \square	omatically (Recommended)
Install the hardware that I manually self	ect from a list (Advanced)
	< <u>B</u> ack <u>N</u> ext> Car
lware	
dware the list below, select the type of hardwar	e you are installing
dware the list below, select the type of hardward	e you are installing
dware the list below, select the type of hardware	e you are installing
dware the list below, select the type of hardware If you do not see the hardware category you v	e you are installing want, click Show All Devices.
Iware the list below, select the type of hardwar If you do not see the hardware category you v	e you are installing want, click Show All Devices.
Iware the list below, select the type of hardwar If you do not see the hardware category you v Common <u>h</u> ardware types:	e you are installing want, click Show All Devices.
Iware the list below, select the type of hardwar If you do not see the hardware category you v Common <u>h</u> ardware types:	e you are installing want, click Show All Devices.
tware the list below, select the type of hardwar f you do not see the hardware category you v Common <u>h</u> ardware types: Multi-port serial adapters Network adapters	e you are installing want, click Show All Devices.
Iware the list below, select the type of hardwar If you do not see the hardware category you v Common <u>h</u> ardware types: Multi-port serial adapters Network adapters PCMCIA adapters Datable Devisor	e you are installing want, click Show All Devices.
the list below, select the type of hardwar If you do not see the hardware category you v Common <u>h</u> ardware types: Multi-port serial adapters Network adapters PCMCIA adapters Portable Devices Portable Devices	e you are installing want, click Show All Devices.
dware the list below, select the type of hardwar If you do not see the hardware category you v Common <u>h</u> ardware types: Multi-port serial adapters Multi-port serial adapters PCMCIA adapters PCMCIA adapters Portable Devices Portable Devices Printers	e you are installing want, click Show All Devices.
the list below, select the type of hardwar f you do not see the hardware category you v Common <u>h</u> ardware types: Multi-port serial adapters Network adapters PCMCIA adapters POrtable Devices Portable Devices Printers SBP2 IEEE 1394 Devices	e you are installing want, click Show All Devices.
the list below, select the type of hardwar If you do not see the hardware category you v Common <u>h</u> ardware types: Multi-port serial adapters Network adapters PCMCIA adapters POMCIA adapters Portable Devices Portable Devices SBP2 IEEE 1394 Devices SD host adapters	e you are installing want, click Show All Devices.
dware the list below, select the type of hardwar If you do not see the hardware category you v Common <u>h</u> ardware types: Multi-port serial adapters Multi-port serial adapters PCMCIA adapters PCMCIA adapters Portable Devices Portable Devices Printers SBP2 IEEE 1394 Devices SD host adapters Scurity Devices	e you are installing want, click Show All Devices.
tware the list below, select the type of hardwar f you do not see the hardware category you v Common <u>h</u> ardware types: Multi-port serial adapters Multi-port serial adapters Network adapters PCMCIA adapters PORCIA adapters Portable Devices Portable Devices SBP2 IEEE 1394 Devices SD host adapters Scurity Devices	e you are installing want, click Show All Devices.
Iware the list below, select the type of hardwar f you do not see the hardware category you v Common <u>h</u> ardware types: Multi-port serial adapters Network adapters PCMCIA adapters Portable Devices Portable Devices Portable Devices SBP2 IEEE 1394 Devices SD host adapters Security Devices	e you are installing want, click Show All Devices.

Add Hardware
Select the device driver you want to install for this hardware.
Select the manufacturer and model of your hardware device and then click Next. If you have a disk that contains the driver you want to install, click Have Disk.
Manufacturer Model (Standard port types) G8BPQ BAFO Technologies Corp. G8BPQ Microsoft Multiport Communications Port Prolific Printer Port
This driver is digitally signed. Have Disk Tell me why driver signing is important
< <u>B</u> ack <u>N</u> ext > Cancel

When you install the first device, you need to select "Have Disk". If you want to install more ports, you can select the G8BPQ entry.

Install Fro	om Disk	×
-	Insert the manufacturer's installation disk, and then make sure that the correct drive is selected below.	OK Cancel
	Copy manufacturer's files from:	Damas

Browse to the place you have installed the files

Add Hardware							
Select the device driver you want to install for this hardware.							
Select the manufacturer and model of your hardware device and then click Next. If you have a disk that contains the driver you want to install, click Have Disk.							
Manufacturer G8BPQ Microsoft	G8BPQ Virtual C	OM Port					
A This driver is not digitally signed Tell me why driver signing is imp	, i! ortant			<u>H</u> av	ve Disk		
Tell me why unversigning is imp							
		< <u>B</u> ack	<u>N</u> e	ext >	Cancel		
Add Hardware The wizard is ready to install your	hardware						
Hardware to install:							
G8BPQ Virtual COM	1 Port						
To start installing your new hardware, click Next.							
		< <u>B</u> ack	Ne	sxt >	Cancel		

You will be warned that you are installing unsigned software.

G8BPQ User Mode Virtual Serial Port Driver Installation Instuctions for Win7+



When you have finished, your device should appear in "Device Manager"



Click here to return.

John Wiseman G8BPQ November 2011